
AIMMS Language Reference - Node and Arc Declaration

This file contains only one chapter of the book. For a free download of the complete book in pdf format, please visit www.aimms.com or order your hard-copy at www.lulu.com/aimms.

Copyright © 1993–2011 by Paragon Decision Technology B.V. All rights reserved.

Paragon Decision Technology B.V.	Paragon Decision Technology Inc.	Paragon Decision Technology Pte.
Schipholweg 1	500 108th Avenue NE	Ltd.
2034 LS Haarlem	Ste. # 1085	80 Raffles Place
The Netherlands	Bellevue, WA 98004	UOB Plaza 1, Level 36-01
Tel.: +31 23 5511512	USA	Singapore 048624
Fax: +31 23 5511517	Tel.: +1 425 458 4024	Tel.: +65 9640 4182
	Fax: +1 425 458 4025	

Email: info@aimms.com
WWW: www.aimms.com

AIMMS is a registered trademark of Paragon Decision Technology B.V. IBM ILOG CPLEX and sc CPLEX is a registered trademark of IBM Corporation. GUROBI is a registered trademark of Gurobi Optimization, Inc. KNITRO is a registered trademark of Ziena Optimization, Inc. XPRESS-MP is a registered trademark of FICO Fair Isaac Corporation. MOSEK is a registered trademark of Mosek ApS. WINDOWS and EXCEL are registered trademarks of Microsoft Corporation. $\text{T}_{\text{E}}\text{X}$, $\text{L}_{\text{A}}\text{T}_{\text{E}}\text{X}$, and $\mathcal{A}\mathcal{M}\mathcal{S}\text{-}\text{L}_{\text{A}}\text{T}_{\text{E}}\text{X}$ are trademarks of the American Mathematical Society. LUCIDA is a registered trademark of Bigelow & Holmes Inc. ACROBAT is a registered trademark of Adobe Systems Inc. Other brands and their products are trademarks of their respective holders.

Information in this document is subject to change without notice and does not represent a commitment on the part of Paragon Decision Technology B.V. The software described in this document is furnished under a license agreement and may only be used and copied in accordance with the terms of the agreement. The documentation may not, in whole or in part, be copied, photocopied, reproduced, translated, or reduced to any electronic medium or machine-readable form without prior consent, in writing, from Paragon Decision Technology B.V.

Paragon Decision Technology B.V. makes no representation or warranty with respect to the adequacy of this documentation or the programs which it describes for any particular purpose or with respect to its adequacy to produce any particular result. In no event shall Paragon Decision Technology B.V., its employees, its contractors or the authors of this documentation be liable for special, direct, indirect or consequential damages, losses, costs, charges, claims, demands, or claims for lost profits, fees or expenses of any nature or kind.

In addition to the foregoing, users should recognize that all complex software systems and their documentation contain errors and omissions. The authors, Paragon Decision Technology B.V. and its employees, and its contractors shall not be responsible under any circumstances for providing information or corrections to errors and omissions discovered at any time in this book or the software it describes, whether or not they are aware of the errors or omissions. The authors, Paragon Decision Technology B.V. and its employees, and its contractors do not recommend the use of the software described in this book for applications in which errors or omissions could threaten life, injury or significant loss.

This documentation was typeset by Paragon Decision Technology B.V. using $\text{L}_{\text{A}}\text{T}_{\text{E}}\text{X}$ and the LUCIDA font family.

Chapter 16

Node and Arc Declaration

This chapter discusses the special identifier types and language constructs that AIMMS offers to allow you to formulate network optimization problems in terms of nodes and arcs. In addition, it is illustrated how you can formulate an optimization problem that consists of a network combined with ordinary variables and constraints.

This chapter

16.1 Networks

There are several model-based applications which contain networks and flows. Typical examples are applications for the distribution of electricity, water, materials, etc. AIMMS offers two special constructs, ARCS and NODES, to formulate flows and flow balances as an alternative to the usual algebraic constructs. Specialized algorithms exist for pure network problems.

Networks

It is possible to intermingle network constructs with ordinary variables and constraints. As a result, the choice between ARCS and VARIABLES on the one hand, and NODES and CONSTRAINTS on the other, becomes a matter of convenience. For instance, in the formulation of a flow balance at a node in the network you can refer to flows along arcs as well as to variables that represent import from outside the network. Similarly, you can formulate an ordinary capacity constraint involving both network flows and ordinary variables.

Mixed formulations

It is assumed here that you know the basics of network flow formulations. Following are three flow-related keywords which can be used to specify a network flow model:

Flow keywords

- **NetInflow**—the total flow into a node minus the total flow out of that node,
- **NetOutflow**—the total flow out of a node minus the total flow into that node, and
- **FlowCost**—the cost function representing the total flow cost built up from individual cost components specified for each arc.

The first two are always used in the context of a node declaration, while the third may be used for the network model declaration.

16.2 NODE declaration and attributes

Each node in a network has a number of associated incoming and outgoing flows. Unless stated otherwise, these flows should be in balance. Based on the flows specified in the model, AIMMS will automatically generate a balancing constraint for every node. The possible attributes of a NODE declaration are given in Table 16.1.

Node attributes

Attribute	Value-type	See also page
INDEX DOMAIN	<i>index-domain</i>	42, 207, 215
UNIT	<i>unit-valued expression</i>	45, 210
TEXT	<i>string</i>	19, 45
COMMENT	<i>comment string</i>	19
DEFINITION	<i>expression</i>	216
PROPERTY	NoSave, Sos1, Sos2, Level, Bound, ShadowPrice, RightHandSideRange, ShadowPriceRange	45, 212, 217

Table 16.1: NODE attributes

Nodes are a special kind of constraint. Therefore, the remarks in Section 14.2 that apply to the attributes of constraints are also valid for nodes. The only difference between constraints and nodes is that in the definition attribute of a node you can use one of the keywords `NetInflow` and `NetOutflow`.

Nodes are like constraints

The keywords `NetInflow` and `NetOutflow` denote the net input or net output flow for the node. The expressions represented by `NetInflow` and `NetOutflow` are computed by AIMMS on the basis of all arcs that depart from and arrive at the declared node. Since these keywords are opposites, you should choose the keyword that makes most sense for a particular node.

NetInflow and NetOutflow

The following two NODE declarations show natural applications of the keywords `NetInflow` and `NetOutflow`.

Example

```

NODE:
  identifier   : CustomerDemandNode
  index domain : (j in Customers, p in Products)
  definition   :
    NetInflow >= ProductDemanded(j,p) ;

NODE:
  identifier   : DepotStockSupplyNode
  index domain : (i in Depots, p in Products)

```

```

definition :
  NetOutflow <= StockAvailable(i,p) + ProductImport(i,p);

```

The declaration of `CustomerDemandNode(c,p)` only involves network flows, while the flow balance of `DepotStockSupplyNode(d,p)` also uses a variable `ProductImport(d,p)`.

16.3 ARC declaration and attributes

Arcs are used to represent the possible flows between nodes in a network. From these flows, balancing constraints can be generated by AIMMS for every node in the network. The possible attributes of an arc are given in Table 16.2.

Arc attributes

Attribute	Value-type	See also page
INDEX DOMAIN	<i>index-domain</i>	42
RANGE	<i>range</i>	207
DEFAULT	<i>constant-expression</i>	44, 209
FROM	<i>node-reference</i>	
FROM MULTIPLIER	<i>expression</i>	
TO	<i>node-reference</i>	
TO MULTIPLIER	<i>expression</i>	
COST	<i>expression</i>	
UNIT	<i>unit-valued expression</i>	210
PRIORITY	<i>expression</i>	210
NONVAR STATUS	<i>expression</i>	211
RELAX STATUS	<i>expression</i>	212
PROPERTY	NoSave, <i>numeric-storage-property</i> , Inline, SemiContinuous, ReducedCost, ValueRange, CoefficientRange	33, 45, 212
TEXT	<i>string</i>	19, 45
COMMENT	<i>comment string</i>	19

Table 16.2: ARC attributes

Arcs play the role of variables in a network problem, but have some extra attributes compared to ordinary variables, namely the FROM, TO, FROM MULTIPLIER, TO MULTIPLIER, and COST attributes. Arcs do not have a DEFINITION attribute because they are implicitly defined by the FROM and TO attributes.

Arcs are like variables

For each arc, the FROM attribute is used to specify the starting node, and the TO attribute to specify the end node. The value of both attributes must be a reference to a declared node.

The FROM and TO attributes

With the FROM MULTIPLIER and TO MULTIPLIER attributes you can specify whether the flow along an arc has a gain or loss factor. Their value must be an expression defined over some or all of the indices of the index domain of the arc. The result of the expression must be positive. If you do not specify a MULTIPLIER attribute, AIMMS assumes a default of one. Network problems with non unit-valued MULTIPLIERS are called *generalized networks*.

The MULTIPLIER attributes

The FROM MULTIPLIER is the conversion factor of the flow at the source node, while the TO MULTIPLIER is the conversion factor at the destination node. Having both multipliers offers you the freedom to specify the network in its most natural way.

FROM and TO MULTIPLIER

You can use the COST attribute to specify the cost associated with the transport of one unit of flow across the arc. Its value is used in the computation of the special variable FlowCost, which is the accumulated cost over all arcs. In the computation of the FlowCost variable the component of an arc is computed as the product of the unit cost and the level value of the flow.

The COST attribute

In the presence of FROM and TO MULTIPLIERS, the drawing in Figure 16.1 illustrates

Graphically illustrated

- the level value of the flow,
- its associated cost component in the predefined FlowCost variable, and
- the flows as they enter into the flow balances at the source and destination nodes (denoted by SBF and DBF, respectively).




Figure 16.1: Flow levels and cost from node i to node j

You can only use the `SemiContinuous` property for arcs if you use an LP solver to find the solution. If you use the pure network solver integrated in AIMMS, AIMMS will issue an error message.

Semi-continuous arcs

Using the declaration of nodes from the previous section, an example of a valid arc declaration is given by

Example

```
ARC:
  identifier : Transport
  index domain : (i,j,p) | Distance(i,j)
  range      : nonnegative
  from       : DepotStockSupplyNode(i,p)
  to         : CustomerDemandNode(j,p)
  cost       : UnitTransportCost(i,j) ;
```

Note that this arc declaration declares flows between nodes i and j for multiple products p .

16.4 Declaration of network-based mathematical programs

If your model contains arcs and nodes, the special variable `FlowCost` can be used in the definition of the objective of your mathematical program. During the model generation phase, AIMMS will generate an expression for this variable based on the associated unit cost for each of the arcs in your mathematical program.

The FlowCost variable

AIMMS will mark your mathematical program as a pure network, if the following conditions are met:

Pure network models

- your mathematical program consists of arcs and nodes only,
- all arcs are continuous and do not have one of the `SOS` or the `SemiContinuous` properties,
- the value of the `OBJECTIVE` attribute equals the variable `FlowCost`, and
- all `MULTIPLIER` attributes assume the default value of one,

For pure network models you can specify `network` as its `TYPE`.

If your mathematical program is a pure network model, AIMMS will pass the model to a special network solver. If your mathematical program is a generalized network or a mixed network-LP problem, AIMMS will generate the constraints associated with the nodes in your network as linear constraints and use an LP solver to solve the problem. AIMMS will also use an LP solver if you have specified its type to be `lp`. You may assert that your mathematical program is a pure network model by specifying `network` as its type.

Network versus LP solver

A pure network model containing the arc and node declarations of the previous sections, but without the additional term $\text{ProductImport}(d,p)$ in the node $\text{DepotStockSupplyNode}(d,p)$, is defined by the following declaration.

Example

```
MATHEMATICAL PROGRAM:
  identifier : ProductFlowDecisionModel
  objective  : FlowCost
  direction  : minimize
  constraints : AllConstraints
  variables  : AllVariables
  type       : network ;
```

If the arc $\text{Transport}(i,j)$ declared in the previous section is the only arc, then the variable FlowCost can be represented by the expression

$$\text{sum} [(i,j,p), \text{UnitTransportCost}(i,j) * \text{Transport}(i,j,p)]$$

Note that the addition of the term $\text{ProductImport}(i,p)$ in $\text{DepotStockSupplyNode}(i,p)$ would result in a mixed network/linear program formulation, which requires an LP solver.